

characters, integer-subscripted elements of Y [Y(1), Y(2), etc.] contain the additional numbers. Y(0) is always returned equal to Y.

Numeric	The canonic value of the number entered by the user; i.e., leading zeros are deleted and trailing zeros after the decimal are deleted.
Pointer	The normal value of Y from a DIC lookup, that is, Internal Entry Number^Entry Name. If the lookup was unsuccessful, Y=-1.
Set of Codes	The internal value of the response.
Yes/No	Y=1 for yes. Y=0 for no
DD (#,#)	The first ^-piece of Y contains the result of the variable X after it has been passed through the INPUT transform of the field specified. Depending on the data type involved, subsequent ^-pieces may contain additional information.

The following list summarizes the values of Y upon timeout, up-arrows, or pressing the Enter/Return keys for all reads. Exceptions are noted.

Condition	Value of Y	Comments
Timeout	Y=""	--
Up-arrow (^)	Y=^	in all cases except end-of-page reads.
Y=0	upon end-of-page reads.	
Double Up-arrow (^ ^)	Y=^^	in all cases except end-of-page reads.