The paging action items in the Action List will appear as follows:

```
Press ENTER or + to go to the next page.  Enter +n to page forward n pages.
Enter = to refresh this page; ^ to exit this list.
****************************************************
.
.
.
.
.
Press ENTER or + to go to the next page.  Enter +n to page forward n pages.
Enter - to go to the previous page.  Enter -n to page back n pages.
Enter 0 to go to the first page; = to refresh this page; ^ to exit.
*****************************************************************************
.
.
.
.
Press ENTER or ^ to exit this list.
Enter - to go to the previous page.  Enter -n to page back n pages.
Enter 0 to go to the first page; = to refresh this page.
```

First Page—The following actions are available when you're on the *first* page of a long list of messages.

Middle Page—The following actions are available when you're on a *middle* page of a long list of messages.

Last Page—The following actions are available when you're on the *last* page of a long list of messages.

Figure 50: MailMan Paging Action Codes

When you have reached the end of a list of messages and press the Return/Enter key or enter the plus sign ("+"), MailMan will ask you if you want to begin again, as shown below:

```
TEST Basket, 45 messages (1-45)
*=New/!=Priority.........Subject...................Lines.From.........Read/Rcvd
   3. [1212173] 12 May 98 Copy of: Test message        55 BLUE,THOMAS E.
   2. [1212124] 12 May 98 test                          1 BLUE,THOMAS E.
   1. [1211500] 06 May 98 Test
Enter message number or command: <RET>

End reached.  Begin again? NO// ?

Enter 'Yes' if you wish to continue reading messages; 'No' if you don't.

End reached.  Begin again? NO//
```

Figure 51: Reaching the End of a List of Messages

If you enter "**Yes**" at the "End reached. Begin again? NO//" prompt, MailMan will redisplay the messages in the basket from the beginning (first page/screen). The order of the messages depends on the order you set in the "MESSAGE ORDER?" field when using the User Options Edit option on the Personal Preferences menu.

*For more information on setting your message display order or the User Options Edit option, please refer to the "How to Choose Your Message Display Order" topic in Chapter 2 in the MailMan V. 7.1 & Patch XM*7.1*50 Getting Started Manual.*